

目录

Table of Content	7
1. Linux Lab Overview	11
1.1 Project Introduction	11
1.2 Project Homepage	11
1.3 Demonstration	13
1.3.1 Free Video Courses In Chinese	13
1.3.2 Non-Free Video Courses In Chinese	13
1.4 Project Functions	14
1.5 Project History	14
1.5.1 Project Origins	14
1.5.2 Problems Solved	14
1.5.3 Project Born	15
2. Linux Lab Installation	16
2.1 Hardware and Software Requirement	17
2.2 Docker Installation	18
2.3 Choose a working directory	19
2.4 Switch to normal user	19
2.5 Download the lab	20
2.6 Run and login the lab	20
2.7 Update and rerun the lab	21
2.8 Quickstart: Boot a board	22
3. Linux Lab Kickstart	23
3.1 Using boards	23
3.1.1 List available boards	23
3.1.2 Choosing a board	25
3.1.2.3 Buy one	27
3.1.3 Using as plugins	27

3.1.4 Configure boards	27
3.2 Build in one command	28
3.3 Detailed Operations	28
3.3.1 Downloading	28
3.3.2 Checking out	29
3.3.3 Patching	29
3.3.4 Configuration	30
3.3.5 Building	31
3.3.6 Saving	31
3.3.7 Booting	31
4. Linux Lab Advance	34
4.1 Using Linux Kernel	34
4.1.1 non-interactive configuration	34
4.1.2 using kernel modules	35
4.1.3 using kernel features	36
4.1.4 Create new development branch	37
4.1.5 Use standalone git repository	38
4.2 Using U-Boot Bootloader	38
4.3 Using QEMU Emulator	40
4.4 Using Toolchains	40
4.5 Using Rootfs	41
4.6 Debugging Linux and U-Boot	42
4.6.1 Debugging Linux	42
4.6.2 Debugging U-Boot	42
4.7 Test Automation	43
4.8 File Sharing	45
4.8.1 Install files to rootfs	45
4.8.2 Share with NFS	45
4.8.3 Transfer via tftp	46
4.8.4 Share with 9p virtio	46

4.9 Learning Assembly	47
4.10 Learning C	48
4.10.1 Host build and Run	48
4.10.2 Cross build and Run	48
4.11 Running any make goals	49
4.12 Speed up kernel development	49
4.12.1 Speed up compiling and save disk life	49
4.12.2 ONESHOT Mode	50
4.12.3 Nolibc Mode	50
4.12.4 Tiny Mode	51
4.13 More Usage	51
5. Linux Lab Development	53
5.1 Choose a board supported by QEMU	53
5.2 Create the board directory	53
5.3 Clone a Makefile from an existing board	53
5.4 Configure the variables from scratch	53
5.5 At the same time, prepare the configs	53
5.6 Choose the versions of kernel, rootfs and U-Boot	54
5.7 Configure, build and boot them	55
5.8 Save the images and configs	55
5.9 Upload everything	55
6. FAQs	57
6.1 Docker Issues	57
6.1.1 Speed up docker images downloading	57
6.1.2 Docker network conflicts with LAN	57
6.1.3 Why not allow running Linux Lab in local host	57
6.1.4 Run tools without sudo	57
6.1.5 Network not work	58
6.1.6 Client.Timeout exceeded while waiting headers	58

6.1.7 Restart Linux Lab after host system shutdown or reboot	59
6.1.8 the following directives are specified both as a flag and in the configuration file	59
6.1.9 pathspec FETCH_HEAD did not match any file known to git	59
6.1.10 Docker not work in Ubuntu 20.04	60
6.1.11 Error creating aufs mount	60
6.2 QEMU Issues	60
6.2.1 Why kvm speeding up is disabled	60
6.2.2 Poweroff hang	61
6.2.3 How to exit QEMU	61
6.2.4 Boot with missing sdl2 libraries failure	61
6.3 Environment Issues	62
6.3.1 NFS/tftpboot not work	62
6.3.2 How to switch Windows in VIM	62
6.3.3 How to delete typo in shell command line	62
6.3.4 Language input switch shortcuts	62
6.3.5 How to tune the screen size	62
6.3.6 How to work in fullscreen mode	64
6.3.7 How to record video	64
6.3.8 Linux Lab not response	64
6.3.9 VNC login with failures	64
6.3.10 Ubuntu Snap Issues	65
6.3.11 How to exit fullscreen mode of vnc clients	65
6.4 Lab Issues	65
6.4.1 No working init found	65
6.4.2 linux/compiler-gcc7.h: No such file or directory	66
6.4.3 linux-lab/configs: Permission denied	66
6.4.4 scripts/Makefile.headersinst: Missing UAPI file	66
6.4.5 unable to create file: net/netfilter/xt_dscp.c	66
6.4.6 how to run as root	67
6.4.7 not in supported list	67

6.4.8 is not a valid rootfs directory	67
7. Contact and Sponsor	68
7.1 Contact Us	68
7.2 Give me a star	68
7.3 Buy our products	68
7.4 Sponsor	69
7.4.1 Sponsor via wechat	69
7.4.2 Sponsor list	69



Figure 1: Linux Lab Logo

Subscribe Wechat :



Figure 2: Wechat Public

Table of Content

- 1. Linux Lab Overview
 - 1.1 Project Introduction
 - 1.2 Project Homepage
 - 1.3 Demonstration
 - 1.3.1 Free Video Courses In Chinese
 - 1.3.2 Non-Free Video Courses In Chinese
 - 1.4 Project Functions
 - 1.5 Project History
 - 1.5.1 Project Origins
 - 1.5.2 Problems Solved
 - 1.5.3 Project Born
- 2. Linux Lab Installation
 - 2.1 Hardware and Software Requirement
 - 2.2 Docker Installation
 - 2.3 Choose a working directory
 - 2.4 Switch to normal user
 - 2.5 Download the lab
 - 2.6 Run and login the lab
 - 2.7 Update and rerun the lab
 - 2.8 Quickstart: Boot a board
- 3. Linux Lab Kickstart
 - 3.1 Using boards
 - 3.1.1 List available boards
 - 3.1.2 Choosing a board
 - 3.1.2.1 Real board
 - 3.1.2.2 Virtual board
 - 3.1.2.3 Buy one
 - 3.1.3 Using as plugins
 - 3.1.4 Configure boards
 - 3.2 Build in one command
 - 3.3 Detailed Operations
 - 3.3.1 Downloading
 - 3.3.2 Checking out
 - 3.3.3 Patching

- 3.3.4 Configuration
 - 3.3.4.1 Default Configuration
 - 3.3.4.2 Manual Configuration
 - 3.3.4.3 Old default configuration
- 3.3.5 Building
- 3.3.6 Saving
- 3.3.7 Booting
- 4. Linux Lab Advance
 - 4.1 Using Linux Kernel
 - 4.1.1 non-interactive configuration
 - 4.1.2 using kernel modules
 - 4.1.3 using kernel features
 - 4.1.3.1 list supported kernel features
 - 4.1.3.2 using kernel modules
 - 4.1.3.3 using rust feature
 - 4.1.3.4 using kft feature
 - 4.1.3.5 using rt feature
 - 4.1.3.6 persist or clear feature setting
 - 4.1.4 Create new development branch
 - 4.1.5 Use standalone git repository
 - 4.2 Using U-Boot Bootloader
 - 4.3 Using QEMU Emulator
 - 4.4 Using Toolchains
 - 4.5 Using Rootfs
 - 4.6 Debugging Linux and U-Boot
 - 4.6.1 Debugging Linux
 - 4.6.2 Debugging U-Boot
 - 4.7 Test Automation
 - 4.8 File Sharing
 - 4.8.1 Install files to rootfs
 - 4.8.2 Share with NFS
 - 4.8.3 Transfer via tftp
 - 4.8.4 Share with 9p virtio
 - 4.9 Learning Assembly
 - 4.10 Learning C

- 4.10.1 Host build and Run
- 4.10.2 Cross build and Run
- 4.11 Running any make goals
- 4.12 Speed up kernel development
 - 4.12.1 Speed up compiling and save disk life
 - 4.12.2 ONESHOT Mode
 - 4.12.3 Nolibc Mode
 - 4.12.4 Tiny Mode
- 4.13 More Usage
- 5. Linux Lab Development
- 5.1 Choose a board supported by QEMU
- 5.2 Create the board directory
- 5.3 Clone a Makefile from an existing board
- 5.4 Configure the variables from scratch
- 5.5 At the same time, prepare the configs
- 5.6 Choose the versions of kernel, rootfs and U-Boot
- 5.7 Configure, build and boot them
- 5.8 Save the images and configs
- 5.9 Upload everything
- 6. FAQs
- 6.1 Docker Issues
 - 6.1.1 Speed up docker images downloading
 - 6.1.2 Docker network conflicts with LAN
 - 6.1.3 Why not allow running Linux Lab in local host
 - 6.1.4 Run tools without sudo
 - 6.1.5 Network not work
 - 6.1.6 Client.Timeout exceeded while waiting headers
 - 6.1.7 Restart Linux Lab after host system shutdown or reboot
 - 6.1.8 the following directives are specified both as a flag and in the configuration file
 - 6.1.9 pathspec FETCH_HEAD did not match any file known to git
 - 6.1.10 Docker not work in Ubuntu 20.04
 - 6.1.11 Error creating aufs mount
- 6.2 QEMU Issues
 - 6.2.1 Why kvm speeding up is disabled
 - 6.2.2 Poweroff hang


- 6.2.3 How to exit QEMU
- 6.2.4 Boot with missing sdl2 libraries failure
- 6.3 Environment Issues
 - 6.3.1 NFS/tftpboot not work
 - 6.3.2 How to switch Windows in VIM
 - 6.3.3 How to delete typo in shell command line
 - 6.3.4 Language input switch shortcuts
 - 6.3.5 How to tune the screen size
 - 6.3.6 How to work in fullscreen mode
 - 6.3.7 How to record video
 - 6.3.8 Linux Lab not response
 - 6.3.9 VNC login with failures
 - 6.3.10 Ubuntu Snap Issues
 - 6.3.11 How to exit fullscreen mode of vnc clients
- 6.4 Lab Issues
 - 6.4.1 No working init found
 - 6.4.2 linux/compiler-gcc7.h: No such file or directory
 - 6.4.3 linux-lab/configs: Permission denied
 - 6.4.4 scripts/Makefile.headersinst: Missing UAPI file
 - 6.4.5 unable to create file: net/netfilter/xt_dscp.c
 - 6.4.6 how to run as root
 - 6.4.7 not in supported list
 - 6.4.8 is not a valid rootfs directory
- 7. Contact and Sponsor
 - 7.1 Contact Us
 - 7.2 Give me a star
 - 7.3 Buy our products
 - 7.4 Sponsor
 - 7.4.1 Sponsor via wechat
 - 7.4.2 Sponsor list

1. Linux Lab Overview

1.1 Project Introduction

This project aims to create a Docker and QEMU based Linux development Lab to easier the learning, development and testing of [Linux Kernel](#).

Linux Lab is open source with no warranty – use at your own risk.



Friendly Notice: TinyLab Community have developed [Linux Lab Disk](#), you can buy from [TinyLab.org's Taobao Shop](#) or [Bilibili Shop](#).

1.2 Project Homepage

- Homepage
 - <https://tinylab.org/linux-lab/>
 - <https://oschina.net/p/linux-lab>
- Repository
 - <https://gitee.com/tinylab/linux-lab>
 - <https://github.com/tinyclub/linux-lab>

Related Projects:

- Cloud Lab
 - Linux Lab Running Environment Manager, provide GUI and CLI, support local and remote login
 - <https://tinylab.org/cloud-lab>
- Linux 0.11 Lab
 - Learning Linux 0.11, only available in Linux Lab Disk from now on
 - Download it to `labs/linux-0.11-lab` and use it in Linux Lab directly
 - <https://tinylab.org/linux-0.11-lab>
- CS630 QEMU Lab
 - Learning X86 Linux Assembly, only available in Linux Lab Disk from now on
 - Download it to `labs/cs630-qemu-lab` and use it in Linux Lab directly
 - <https://tinylab.org/cs630-qemu-lab>
- RVOS Lab
 - Learning RISC-V OS course, merged in [Linux Lab Disk](#)
 - Download it to `src/examples` and use it in Linux Lab directly
 - <https://gitee.com/tinylab/rvos-lab>
- GUI Lab
 - Learning embedded GUI (e.g. Guilite), merged in [Linux Lab Disk](#)
 - Download it to `src/examples` and use it in Linux Lab directly
 - <https://gitee.com/tinylab/gui-lab>
- RISC-V Linux
 - Learning RISC-V Linux kernel, merged in [Linux Lab Disk](#)
 - Download it to `src/examples` and use it in Linux Lab directly
 - <https://gitee.com/tinylab/riscv-linux>
- RISC-V Lab
 - Learning embedded RISC-V software development, merged in [Linux Lab Disk](#) for RISC-V
 - <https://gitee.com/tinylab/riscv-lab>
- ARM Lab
 - Learning embedded ARM software development, merged in [Linux Lab Disk](#) for ARM
 - <https://gitee.com/tinylab/arm-lab>

1.3 Demonstration

1.3.1 Free Video Courses In Chinese

- [Linux Lab Open Videos](#)
 - Linux Lab Introduction
 - Loongson Linux Development
 - Linux Lab Disk Demonstration
 - Linux Lab Release Meeting Replay Videos
 - Rust For Linux Introduction
- [Linux Kernel Observation](#)
- [RISC-V Linux Kernel Investigation](#)
- RISC-V Linux System Development Course
 - [Part I: Embedded Quickstart][<https://space.bilibili.com/687228362/channel/collectiondetail?sid=1750690>], Require [Linux RISC-V Disk](#)
 - [Part II: Embedded Practice][<https://space.bilibili.com/687228362/channel/collectiondetail?sid=2021659>], Require [Tiny RISC-V Box](#)
 - [Part III: Embedded Advance][<https://space.bilibili.com/687228362/channel/collectiondetail?sid=3128538>], Require [Tiny RISC-V Box](#)

1.3.2 Non-Free Video Courses In Chinese

- [《The Perspective of Linux ELF》](#)
 - Learn Linux ELF by practice, with hundreds of examples, all verified in Linux Lab
- [《Rust Language Quickstart》](#)
 - Rust course for C programmer, with examples verified in Linux Lab
- [《Software Reverse Engineering Quickstart》](#)
 - Learn reverse engineering by practice, with examples verified in Linux Lab
- [《Linux Kernel Livepatch Introduction》](#)
 - Learn Linux live patching in AArch64 by practice, with examples verified in Linux Lab

1.4 Project Functions

Now, Linux Lab becomes an intergrated Linux learning, development and testing environment, it supports:

Items	Description
Boards	QEMU based, 7+ main Architectures, 20+ popular boards; Several real boards support
Components	Uboot, Linux / Modules, Buildroot, Qemu, Linux v0.11, v2.6.10 ~ 5.x supported
Prebuilt	All of above components have been prebuilt
Rootfs	Support include initrd, harddisk, mmc and nfs, Debian availab for ARM
Docker	Cross toolchains from gcc-4.3 available in one command, external ones configurable
Access	Accessible from local or remote, include CLI and GUI, support bash, ssh, vnc, web vnc
Network	Builtin bridge networking, every board has network (except Raspi3)
Boot	Support serial port, curses (bash/ssh friendly) and graphic booting
Testing	Support automatic testing via <code>make test</code> target
Debugging	debuggable via <code>make debug</code> target

Continue reading for more features and usage.

1.5 Project History

1.5.1 Project Origins

About 10 years ago (2010), a tinylinux proposal: [Work on Tiny Linux Kernel](#) accepted by Embedded Linux Foundation, therefore I have worked on this project for serveral months.

1.5.2 Problems Solved

During the project cycle, several scripts written to verify if the adding tiny features (e.g. [gc-sections](#)) breaks the other kernel features on the main CPU architectures.

These scripts uses qemu-system-ARCH as the cpu/board simulator, basic boot+function tests have been done for ftrace+perf, accordingly, defconfigs, rootfs, test scripts have been prepared, at that time, all of them were simply put in a directory, without a design or holistic consideration.

1.5.3 Project Born

They have slept in my harddisk for several years without any attention, until one day, docker and novnc came to my world, at first, [Linux 0.11 Lab](#) was born, after that, Linux Lab was designed to unify all of the above scripts, defconfigs, rootfs and test scripts.

2. Linux Lab Installation

Linux Lab uses Docker, if have already installed Docker and configured the best mirror site of docker images, it is very easy to install Linux Lab.

If really a Linux newbie or simply don't want to spend time on boring installation, buy the instant Linux Lab Disk:



It supports:

- Capacity
 - From 32G to 512G and even 1T, 2T, 4T
- Products
 - High Speed U Disk, Solid U Disk, Portable disk, Solid disk (NVME / SATA)
- Systems
 - Top6 Linux Distributions and even more based on your requirement
 - Include Ubuntu 18.04-22.04, Deepin 20.8+, Fedora 37+, Mint 21.1+, Kali, Manjaro
- Features

- Boot from any powered-off 64bit X86 Machine, include PC, Laptop and Mac-Book
 - Boot from any running Windows, Linux and run in parallel with them
 - Switch from or to any running Windows, Linux without poweroff
 - Multiple Linux Lab Disks can boot or switch from/to each other
 - Support timezone setting of different systems transparently, without manual setting
 - Share files and clipboards automatically between the main system and our disk system
 - Support transparent compress, use 128G as ~256G capacity
 - Support memory compiling, speedup compiling and save disk erase life
 - Support factory restore, allow restore factory system in some cases
 - Support volatile memory booting, allow read and write from memory, faster and longer
 - Merged in many labs, such as Linux Lab, Linux 0.11 Lab, be able to learn Linux kernel, embedded Linux, Uboot, Assembly, C, Python, Database, Network and so forth
- Where to buy
 - [Taobao shop of TinyLab.org Community](#)
 - [Bilibili Shop](#)
 - Product details
 - <https://tinylab.org/linux-lab-disk>
 - Introduce and demonstrate the features, functions and usage of Linux Lab Disk

2.1 Hardware and Software Requirement

Linux Lab is a full embedded Linux development system, it needs enough calculation capacity and disk & memory storage space, to avoid potential extension issues, here is the recommended configuration:

Hardware	Requirement	Description
Processor	X86_64, > 1.5GHz	Must choose 64bit X86 while using virtual machine
Disk	>= 50G	System (25G), Docker Images(~5G), Linux Lab (20G)
Memory	>= 4G	Lower than 4G may have many unpredictable exceptions

If often use, please increase disk storage to 100G~200G, memory storage to 8G, cpu cores to 4 and above.

Currently, all of the X86_64 systems support Docker should be able to run Linux Lab, include Windows, Linux and MacOS, all of the popular Linux distributions may have been tried by different users.

Welcome to take a look at [the systems running Linux Lab](#) and share yours, for example:

```
1 $ cd /path/to/cloud-lab
2 $ tools/docker/env
3 System: Ubuntu 16.04.6 LTS
4 Linux: 4.4.0-176-generic
5 Docker: Docker version 18.09.4, build d14af54
```

2.2 Docker Installation

Docker is required by Linux Lab, please install it at first:

- Linux, Mac OSX, Windows 10

[Docker CE](#)

- older Windows (include some older Windows 10)

[Docker Toolbox](#); Install Ubuntu via Virtualbox or Vmware Virtual Machine

Before running Linux Lab, please refer to section 6.1.4 and make sure the following command works without sudo and without any issue:

```
1 $ docker run hello-world
```

In China, to use docker service normally, please **must** configure one of chinese docker mirror sites, for example:

- [Aliyun Docker Mirror Documentation](#)
 - For non Univerisity users, require login with freely registered account
- [USTC Docker Mirror Documentation](#)
 - For Univerisity users

More docker related issues, such as download slowly, download timeout and download errors, are clearly documented in the 6.1 section of FAQs.

The other issues, please read the [official docker docs](#).

Notes for Ubuntu Users - [doc/install/ubuntu-docker.md](#)

Notes for Arch Users - [doc/install/arch-docker.md](#)

Notes for Manjaro Users - [doc/install/manjaro-docker.md](#)

Notes for Windows Users:

- Please make sure your Windows version support docker: [Official Docker Documentation](#) and determine Docker Desktop or Docker Toolbox should be used
- Linux Lab only tested with ‘Git Bash’ in Windows, please must use with it
 - After installing [Git For Windows](#), “Git Bash Here” will come out in right-button press menu

2.3 Choose a working directory

Please simply choose one directory in `~/Downloads` OR `~/Documents` OR create a new `~/Develop` directory.

```
1 $ mkdir ~/Develop
2 $ cd ~/Develop
```

For Windows and Mac OSX, to compile Linux normally, please refer to section 5.7.1 and enable building cache:

2.4 Switch to normal user

Before downloading Linux Lab, please **MUST** switch to normal user.

Check who am i, 0 means root, non-zero means normal user:

```
1 $ id -u `whoami`
2 1000
```

If current user is `root`, switch to a normal one:

```
1 # id -u `whoami`
2 0
3 # sudo -su <USER>
```

If no normal user exists, create new:

```
1 $ sudo useradd --create-home --shell /bin/bash --user-group --groups adm,sudo laber
2 $ sudo passwd laber
3 $ sudo -su laber
4 $ whoami
5 laber
```

2.5 Download the lab

Use Ubuntu system as an example:

Download cloud lab framework with normal user, pull images and checkout linux-lab repository:

```
1 $ git clone https://gitee.com/tinylab/cloud-lab.git
2 $ cd cloud-lab/
```

If cloned source code with `root` account, please **MUST** switch to normal user and change their owner:

```
1 $ sudo -su <USER>
2 $ sudo chown -R <USER>:<USER> -R cloud-lab/{*,.git}
```

2.6 Run and login the lab

Launch the lab and login with the user and password printed in the console:

```
1 $ tools/docker/run linux-lab
```

Login with Bash:

```
1 $ tools/docker/bash
```

Re-login the lab via web browser:

```
1 $ tools/docker/webvnc
```

The other login methods:

```
1 $ tools/docker/vnc
2 $ tools/docker/ssh
3 $ tools/docker/webssh
```

Choose one of the methods:

```
1 $ tools/docker/login list # List, choose and record
2 $ tools/docker/login vnc # Choose one directly and record for late login
```

Summary of login methods:

Login Method	Description	Default User	Where
bash	docker bash	Ubuntu	localhost
ssh	normal ssh	Ubuntu	localhost
vnc	normal vnc	Ubuntu	localhost+VNC client
webvnc	web desktop	Ubuntu	anywhere via internet
webssh	web ssh	Ubuntu	anywhere via internet

Since vnc clients differs from operating systems, we use webvnc by default to make sure auto login vnc for all systems.

If really want to use local vnc clients, please install a vnc client, for example: `vinagre`, then specify it like this:

```
1 $ tools/docker/vnc vinagre
```

If the above command not work normally, based on the information printed above, please configure the vnc client yourself.

Notes:

- `vinagre` has fullscreen mode, but not enabled by default, which can be enabled through menu: `View -> Fullscreen`, but must enable `Keyboard shortcuts` at first, otherwise, no way exit fullscreen except via `sudo pkill x11vnc`.
- The directly connected ssh and vnc may not always work, please use one of the other three methods instead.

2.7 Update and rerun the lab

Usually, only need to update Linux Lab itself, to get the new boards support or related fixups:

```
1 $ cd /path/to/cloud-lab/labs/linux-lab/  
2 $ git checkout master  
3 $ git pull
```

Sometimes, need to update Cloud Lab, to fix up potential running issues or getting newer docker image:

```
1 $ cd /path/to/cloud-lab  
2 $ git checkout master  
3 $ git pull
```

If modified the running environment of Linux Lab locally and want to reuse it in the future, save the container (very slow, not recommend if not necessary):

```
1 $ tools/docker/save linux-lab  
2 $ git checkout -- configs/linux-lab/docker/name
```

Then rerun Linux lab:

```
1 $ tools/docker/rerun linux-lab
```

2.8 Quickstart: Boot a board

Get into the lab environment, switch directory:

```
1 $ cd /labs/linux-lab
```

Issue the following command to boot the prebuilt kernel and rootfs on the default `vexpress-a9` board:

```
1 $ make boot
```

Login as `root` user without password(password is empty), just input `root` and press Enter:

```
1 Welcome to Linux Lab
2
3 linux-lab login: root
4
5 # uname -a
6 Linux linux-lab 5.1.0 #3 SMP Thu May 30 08:44:37 UTC 2019 armv7l GNU/Linux
7 #
8 # poweroff
9 #
```

Shutdown the board with the `poweroff` command.

****Notes**:** If some boards not support `poweroff`, please press `CTRL+a x`. Of course, open another terminal and issue `kill` or `pkill` command also can quit `qemu`.

3. Linux Lab Kickstart

3.1 Using boards

3.1.1 List available boards

List builtin boards:

```

1  $ make list
2  [ aarch64/raspi3 ]:
3      ARCH      = arm64
4      CPU       ?= cortex-a53
5      LINUX    ?= v5.1
6      ROOTDEV_LIST := /dev/mmcblk0 /dev/ram0
7      ROOTDEV  ?= /dev/mmcblk0
8  [ aarch64/virt ]:
9      ARCH      = arm64
10     CPU       ?= cortex-a57
11     LINUX    ?= v5.1
12     ROOTDEV_LIST := /dev/sda /dev/vda /dev/ram0 /dev/nfs
13     ROOTDEV  ?= /dev/vda
14  [ arm/mcimx6ul-evk ]:
15     ARCH      = arm
16     CPU       ?= cortex-a9
17     LINUX    ?= v5.4
18     ROOTDEV_LIST := /dev/mmcblk0 /dev/ram0 /dev/nfs
19     ROOTDEV  ?= /dev/mmcblk0
20  [ arm/versatilepb ]:
21     ARCH      = arm
22     CPU       ?= arm926t
23     LINUX    ?= v5.1
24     ROOTDEV_LIST := /dev/sda /dev/ram0 /dev/nfs
25     ROOTDEV  ?= /dev/ram0
26  [ arm/vexpress-a9 ]:
27     ARCH      = arm
28     CPU       ?= cortex-a9
29     LINUX    ?= v5.1
30     ROOTDEV_LIST := /dev/mmcblk0 /dev/ram0 /dev/nfs
31     ROOTDEV  ?= /dev/ram0
32  [ i386/pc ]:
33     ARCH      = x86
34     CPU       ?= qemu32
35     LINUX    ?= v5.1
36     ROOTDEV_LIST ?= /dev/hda /dev/ram0 /dev/nfs
37     ROOTDEV_LIST[LINUX_v2.6.34.9] ?= /dev/sda /dev/ram0 /dev/nfs
38     ROOTDEV  ?= /dev/hda
39  [ mips64el/ls2k ]:
40     ARCH      = mips
41     CPU       ?= mips64r2
42     LINUX    ?= loongnix-release-1903
43     LINUX[LINUX_loongnix-release-1903] := 04b98684
44     ROOTDEV_LIST := /dev/sda /dev/ram0 /dev/nfs
45     ROOTDEV  ?= /dev/ram0
46  [ mips64el/ls3a7a ]:
47     ARCH      = mips
48     CPU       ?= mips64r2
49     LINUX    ?= loongnix-release-1903
50     LINUX[LINUX_loongnix-release-1903] := 04b98684
51     ROOTDEV_LIST ?= /dev/sda /dev/ram0 /dev/nfs

```

```
52     ROOTDEV ?= /dev/ram0
53 [ mipsel/ls1b ]:
54     ARCH     = mips
55     CPU      ?= mips32r2
56     LINUX    ?= v5.2
57     ROOTDEV_LIST ?= /dev/ram0 /dev/nfs
58     ROOTDEV ?= /dev/ram0
59 [ mipsel/ls232 ]:
60     ARCH     = mips
61     CPU      ?= mips32r2
62     LINUX    ?= v2.6.32-r190726
63     ROOTDEV_LIST := /dev/ram0 /dev/nfs
64     ROOTDEV ?= /dev/ram0
65 [ mipsel/malta ]:
66     ARCH     = mips
67     CPU      ?= mips32r2
68     LINUX    ?= v5.1
69     ROOTDEV_LIST := /dev/hda /dev/ram0 /dev/nfs
70     ROOTDEV ?= /dev/ram0
71 [ ppc/g3beige ]:
72     ARCH     = powerpc
73     CPU      ?= generic
74     LINUX    ?= v5.1
75     ROOTDEV_LIST := /dev/hda /dev/ram0 /dev/nfs
76     ROOTDEV ?= /dev/ram0
77 [ riscv32/virt ]:
78     ARCH     = riscv
79     CPU      ?= any
80     LINUX    ?= v5.0.13
81     ROOTDEV_LIST := /dev/vda /dev/ram0 /dev/nfs
82     ROOTDEV ?= /dev/vda
83 [ riscv64/virt ]:
84     ARCH     = riscv
85     CPU      ?= any
86     LINUX    ?= v5.1
87     ROOTDEV_LIST := /dev/vda /dev/ram0 /dev/nfs
88     ROOTDEV ?= /dev/vda
89 [ x86_64/pc ]:
90     ARCH     = x86
91     CPU      ?= qemu64
92     LINUX    ?= v5.1
93     ROOTDEV_LIST := /dev/hda /dev/ram0 /dev/nfs
94     ROOTDEV_LIST[LINUX_v3.2] := /dev/sda /dev/ram0 /dev/nfs
95     ROOTDEV ?= /dev/ram0
96 [ csky/virt ]:
97     ARCH     = csky
98     CPU      ?= ck810
99     LINUX    ?= v4.9.56
100    ROOTDEV ?= /dev/nfs
```

ARCH, FILTER arguments are supported:

```
1 $ make list ARCH=arm
2 $ make list FILTER=virt
```

and more:

```
1 $ make list-board      # only ARCH
2 $ make list-short     # ARCH and Linux
3 $ make list-base      # no plugin
```



```
4 $ make list-plugin      # only plugin
5 $ make list-full       # everything
6 $ make list-real       # real hardware boards
7 $ make list-virt       # only virtual boards
```

3.1.2 Choosing a board


3.1.2.1 Real board

From version v0.6, to support learn external devices, Linux Lab adds real hardware board support, to use such boards, please buy them and connect them to your develop host correctly.

Only list real boards:

```
1 $ make list-real
2 [ arm/ebf-imx6ull ]:
3 ARCH      = arm
4 CPU       ?= cortex-a9
5 LINUX     ?= v4.19.35
6 ROOTDEV_LIST := /dev/mmcblk0 /dev/ram0 /dev/nfs
7 ROOTDEV   ?= /dev/mmcblk0
```

Because real hardware boards differs from each other, so, board specific document are recommended, for example: `boards/arm/ebf-imx6ull/README.md`.



3.1.2.2 Virtual board

By default, the default virtual board: `vexpress-a9` is used, we can configure, build and boot for a specific board with `BOARD`, for example:

```
1 $ make BOARD=malta
2 $ make boot
```

If several boards have the same name, please specify the architecture to distinguish:

```
1 $ make BOARD=mipsel/malta
```

Currently, such boards have the same name:

```
1 $ make list FILTER=virt
2 [ aarch64/virt ]:
3     ARCH    = arm64
4     CPU     ?= cortex-a57
5     LINUX   ?= v5.1
6     ROOTDEV_LIST := /dev/sda /dev/vda /dev/ram0 /dev/nfs
7     ROOTDEV ?= /dev/vda
8 [ riscv32/virt ]:
9     ARCH    = riscv
10    CPU     ?= any
11    LINUX   ?= v5.0.13
12    ROOTDEV_LIST := /dev/vda /dev/ram0 /dev/nfs
13    ROOTDEV ?= /dev/vda
14 [ riscv64/virt ]:
15    ARCH    = riscv
16    CPU     ?= any
17    LINUX   ?= v5.1
18    ROOTDEV_LIST := /dev/vda /dev/ram0 /dev/nfs
19    ROOTDEV ?= /dev/vda
20
21 $ make list FILTER=/pc
22 [ i386/pc ]:
23     ARCH    = x86
24     CPU     ?= qemu32
25     LINUX   ?= v5.1
26     ROOTDEV_LIST ?= /dev/hda /dev/ram0 /dev/nfs
27     ROOTDEV_LIST[LINUX_v2.6.34.9] ?= /dev/sda /dev/ram0 /dev/nfs
28     ROOTDEV ?= /dev/hda
29 [ x86_64/pc ]:
30     ARCH    = x86
31     CPU     ?= qemu64
32     LINUX   ?= v5.1
33     ROOTDEV_LIST := /dev/hda /dev/ram0 /dev/nfs
34     ROOTDEV_LIST[LINUX_v3.2] := /dev/sda /dev/ram0 /dev/nfs
35     ROOTDEV ?= /dev/ram0
```

Use them like this:

```
1 $ make BOARD=x86_64/pc
2 $ make BOARD=riscv64/virt
```

If using `board`, it only works on-the-fly, the setting will not be saved, this is helpful to run multiple boards at the same and not to disrupt each other:

```
1 $ make board=malta boot
```

This allows to run multi boards in different terminals or background at the same time.

Check the board specific configuration:

```
1 $ cat boards/arm/vexpress-a9/Makefile
```

Notes: More money are required to maintain this project, only one virtual board is free now, the others are non-free, buy one as you want.

3.1.2.3 Buy one

All supported real hardware boards, virtual hardware boards support and the related Linux Lab Disk will be put in [TinyLab.org's Taobao Shop](#) or [Bilibili Shop](#), after bought them, please contact with wechat: `tinylab` and join in the development group.

3.1.3 Using as plugins

The 'Plugin' feature is supported by Linux Lab, to allow boards being added and maintained in standalone git repositories. Standalone repository is very important to ensure Linux Lab itself not grow up big and big while more and more boards being added in.

Book examples or the boards with a whole new CPU architecture benefit from such feature a lot, for book examples may use many boards and a new CPU architecture may need require lots of new packages (such as cross toolchains and the architecture specific QEMU system tool).

Here maintains the available plugins:

- [C-Sky Linux](#)
- [Loongson Linux](#)

The Loongson plugin has been merged into v5.0.

3.1.4 Configure boards

Every board has its own configuration, some can be changed on demand, for example, memory size, linux version, buildroot version, qemu version and the other external devices, such as serial port, network devices and so on.

The configure method is very simple, just edit it by referring to current values (`boards/<BOARD>/Makefile`), this command open local configuration (`boards/<BOARD>/labconfig`) via vim:

```
1 $ make edit
```

But please don't make a big change once, we often only need to tune Linux version, this command is better for such case:

```
1 $ make list-linux
2 v4.12 v4.5.5 v5.0.10 [v5.1]
3 $ make config LINUX=v5.0.10
4 $ make list-linux
5 v4.12 v4.5.5 [v5.0.10] v5.1
```

If want to upstream your local changes, please use `board-edit` and `board-config`, otherwise, `edit` and `config` are preferable, for they will avoid conflicts while pulling remote updates.

3.2 Build in one command

v0.3+ version add target dependency by default, so, if want to compile a kernel, just run:

```
1 $ make kernel-build
2
3 Or
4
5 $ make build kernel
```

It will do everything required, of course, we still be able to run the targets explicitly.

And futher, with the timestamping support, finished targets will not be run again during the late operations, if still want, just clean the stamp and run it again:

```
1 $ make cleanstamp kernel-build
2 $ make kernel-build
3
4 Or
5
6 $ make force-kernel-build
```

To clean all of the stamp files:

```
1 $ make cleanstamp kernel
```

This function also support uboot, root and qemu.

3.3 Detailed Operations

3.3.1 Downloading

Download board specific package and the kernel, buildroot source code:

```
1 $ make source APP=bsp,kernel,root,uboot
2 Or
3 $ make source APP=all
4 Or
5 $ make source all
```

Download one by one:

```
1 $ make bsp-source
2 $ make kernel-source
3 $ make root-source
4 $ make uboot-source
5
6 Or
7
8 $ make source bsp
9 $ make source kernel
10 $ make source root
11 $ make source uboot
```

After v0.5, the source code are downloaded in `src/`, before, they are saved in the root directory of Linux Lab.

Notes: the source code will be downloaded to `build/src` when `CACHE_SRC` or `ONESHOT` is configured to 1, please save or backup the data inside manually, otherwise, they will be lost after system poweroff.

3.3.2 Checking out

Checkout the target version of kernel and builroot:

```
1 $ make checkout APP=kernel,root
```

Checkout them one by one:

```
1 $ make kernel-checkout
2 $ make root-checkout
3
4 Or
5
6 $ make checkout kernel
7 $ make checkout root
```

If checkout not work due to local changes, save changes and run to get a clean environment:

```
1 $ make kernel-cleanup
2 $ make root-cleanup
3
4 Or
5
6 $ make cleanup kernel
7 $ make cleanup root
```

The same to QEMU and U-Boot.

3.3.3 Patching

Apply available patches in `boards/<BOARD>/bsp/patch/linux` and `src/patch/linux/`:

```
1 $ make kernel-patch
2
3 Or
4
5 $ make patch kernel
```

3.3.4 Configuration

3.3.4.1 Default Configuration

Configure kernel and buildroot with defconfig:

```
1 $ make defconfig APP=kernel,root
```

Configure one by one, by default, use the defconfig in `boards/<BOARD>/bsp/`:

```
1 $ make kernel-defconfig
2 $ make root-defconfig
3
4 Or
5
6 $ make defconfig kernel
7 $ make defconfig root
```

Configure with specified defconfig:

```
1 $ make B=rspi3
2 $ make kernel-defconfig bcmrpi3_defconfig
3 $ make root-defconfig raspberrypi3_64_defconfig
```

If only defconfig name specified, search `boards/` at first, and then the default configs path of buildroot, u-boot and linux-stable respectively: `src/buildroot/configs`, `src/u-boot/configs`, `src/linux-stable/arch//configs`.

3.3.4.2 Manual Configuration

```
1 $ make kernel-menuconfig
2 $ make root-menuconfig
3
4 Or
5
6 $ make menuconfig kernel
7 $ make menuconfig root
```

3.3.4.3 Old default configuration

```
1 $ make kernel-olddefconfig
2 $ make root-olddefconfig
3 $ make uboot-olddefconfig
4
5 Or
6
```

```
7 $ make olddefconfig kernel
8 $ make olddefconfig root
9 $ make olddefconfig uboot
```

3.3.5 Building

Build kernel and buildroot together:

```
1 $ make build APP=kernel,root
```

Build them one by one:

```
1 $ make kernel-build # make kernel
2 $ make root-build # make root
3
4 Or
5
6 $ make build kernel
7 $ make build root
```

After v0.5, the building result are stored in `build/`, before they are put in `output/`.

3.3.6 Saving

Save all of the configs and rootfs/kernel/dtb images:

```
1 $ make save APP=kernel,root
2 $ make saveconfig APP=kernel,root
```

Save configs and images to `boards/<BOARD>/bsp/`:

```
1 $ make kernel-saveconfig
2 $ make root-saveconfig
3 $ make root-save
4 $ make kernel-save
5
6 Or
7
8 $ make saveconfig kernel
9 $ make saveconfig root
10 $ make save kernel
11 $ make save root
```

3.3.7 Booting

Boot with serial port (nographic) by default, exit with `CTRL+a x`, `poweroff`, `reboot` OR `pkill qemu` (See [poweroff hang](#)):

```
1 $ make boot
```

Boot with graphic (Exit with `CTRL+ALT+2 quit`):

```
1 $ make b=pc boot G=1 LINUX=v5.1 BUILDROOT=2019.11
2 $ make b=versatilepb boot G=1 LINUX=v5.1 BUILDROOT=2016.05
3 $ make b=g3beige boot G=1 LINUX=v5.1 BUILDROOT=2016.05
4 $ make b=malta boot G=1 LINUX=v2.6.36 BUILDROOT=2016.05
5 $ make b=vexpress-a9 boot G=1 LINUX=v4.6.7 BUILDROOT=2016.05 // LINUX=v3.18.39 works too
```

Note:

- real graphic boot require LCD and keyboard drivers, the above boards work well, with Linux v5.1, `raspi3` and `malta` has `tty0` console but without keyboard input.
- new buildroot config files set tty console to serial with (`BR2_TARGET_GENERIC_GETTY_PORT="ttyAMA0"`), to enable console with `G=1`, please change the `getty` line in `/etc/inittab`, for example, replace `ttyAMA0` with `console`, we can also simply switch to the serial console via the Qemu ‘View’ menu.

`vexpress-a9` and `virt` has no LCD support by default, but for the latest `qemu`, it is able to boot with `G=1` and switch to serial console via the ‘View’ menu, this can not be used to test LCD and keyboard drivers. `QOPTS` specify the additional QEMU options.

```
1 $ make b=vexpress-a9 CONSOLE=ttyAMA0 boot G=1 LINUX=v5.1
2 $ make b=raspi3 CONSOLE=ttyAMA0 QOPTS="-serial vc -serial vc" boot G=1 LINUX=v5.1
```

Boot with curses graphic (friendly to bash/ssh login, not work for all boards, exit with `ESC+2` quit OR `ALT+2` quit):

```
1 $ make b=pc boot G=2 LINUX=v4.6.7
```

Boot with PreBuilt Kernel, Dtb and Rootfs:

```
1 $ make boot kernel=old dtb=old root=old
```

Boot with new kernel, dtb and rootfs if exists:

```
1 $ make boot kernel=new dtb=new root=new
```

Boot with new kernel and uboot, build them if not exists:

```
1 $ make boot BUILD=kernel,uboot
```

Boot without Uboot (only `versatilepb` and `vexpress-a9` boards tested):

```
1 $ make boot U=0
```

Boot with different rootfs (depends on board, check `/dev/` after boot):

```
1 $ make boot ROOTDEV=ram0 // support by all boards, basic boot method
2 $ make boot ROOTDEV=nfs // depends on network driver, only raspi3 not work
3 $ make boot ROOTDEV=sda
4 $ make boot ROOTDEV=mmcblk0
5 $ make boot ROOTDEV=vda // virtio based block device
```


Boot with extra kernel command line (KCLI = Additional Kernel Command Line):

```
1 $ make boot ROOTDEV=nfs KCLI="init=/bin/bash"
```

List supported options:

```
1 $ make list ROOTDEV
2 $ make list BOOTDEV
3 $ make list CCOR1
4 $ make list NETDEV
5 $ make list linux
6 $ make list uboot
7 $ make list qemu
```

And more <xxx>-list are also supported with `list <xxx>`, for example:

```
1 $ make list features
2 $ make list modules
3 $ make list gcc
```

4. Linux Lab Advance

4.1 Using Linux Kernel

4.1.1 non-interactive configuration

A tool named `scripts/config` in Linux kernel is helpful to get/set the kernel config options non-interactively, based on it, both of `kernel-getconfig` and `kernel-setconfig` are added to tune the kernel options, with them, we can simply “enable/disable/setstr/setval/getstate” of a kernel option or many at the same time:

Get state of a kernel module:

```
1 $ make kernel-getconfig m=minix_fs
2 Getting kernel config: MINIX_FS ...
3
4 build/aarch64/linux-v5.1-virt/.config:CONFIG_MINIX_FS=m
```

Enable a kernel module:

```
1 $ make kernel-setconfig m=minix_fs
2 Setting kernel config: m=minix_fs ...
3
4 build/aarch64/linux-v5.1-virt/.config:CONFIG_MINIX_FS=m
5
6 Enable new kernel config: minix_fs ...
```

More control commands of `kernel-setconfig` including `y`, `n`, `c`, `o`, `s`, `v`:

Option	Description
<code>y</code>	build the modules in kernel or enable another kernel options.
<code>c</code>	build the modules as pluginable modules, just like <code>m</code> .
<code>o</code>	build the modules as pluginable modules, just like <code>m</code> .
<code>n</code>	disable a kernel option.
<code>s</code>	<code>RTC_SYSTOHC_DEVICE="rtc0"</code> , set the rtc device to <code>rtc0</code>
<code>v</code>	<code>PANIC_TIMEOUT=5</code> , set the kernel panic timeout to 5 secs.

Operates many options in one command line:

```
1 $ make kernel-setconfig m=tun,minix_fs y=ikconfig v=panic_timeout=5 s=DEFAULT_HOSTNAME=
   linux-lab n=debug_info
2 $ make kernel-getconfig o=tun,minix,ikconfig,panic_timeout,hostname
```

4.1.2 using kernel modules

Build all internal kernel modules:

```
1 $ make modules
2 $ make modules-install
3 $ make root-rebuild // not need for nfs boot
4 $ make boot
```

List available modules in `src/modules/`, `boards/<BOARD>/bsp/modules/`:

```
1 $ make modules-list
```

If `m` argument specified, list available modules in `src/modules/`, `boards/<BOARD>/bsp/modules/` and `src/linux-stable/`:

```
1 $ make modules-list m=hello
2     1     m=hello ; M=$PWD/src/modules/hello
3 $ make modules-list m=tun,minix
4     1     c=TUN ; m=tun ; M=drivers/net
5     2     c=MINIX_FS ; m=minix ; M=fs/minix
```

Enable one kernel module:

```
1 $ make kernel-getconfig m=minix_fs
2 Getting kernel config: MINIX_FS ...
3
4 build/aarch64/linux-v5.1-virt/.config:CONFIG_MINIX_FS=m
5
6 $ make kernel-setconfig m=minix_fs
7 Setting kernel config: m=minix_fs ...
8
9 build/aarch64/linux-v5.1-virt/.config:CONFIG_MINIX_FS=m
10
11 Enable new kernel config: minix_fs ...
```

Build one kernel module (e.g. `minix.ko`):

```
1 $ make modules M=fs/minix/
2 Or
3 $ make modules m=minix
```

Install and clean the module:

```
1 $ make modules-install M=fs/minix/
2 $ make modules-clean M=fs/minix/
```

More flexible usage:

```
1 $ make kernel-setconfig m=tun
2 $ make kernel tun.ko M=drivers/net
3 $ make kernel drivers/net/tun.ko
```

Build external kernel modules (the same as internal modules):

```
1 $ make modules m=hello
2 Or
3 $ make kernel x=$PWD/modules/hello/hello.ko
```

4.1.3 using kernel features

4.1.3.1 list supported kernel features

Kernel features are abstracted in `src/feature/linux/`, including their configurations patch-set, it can be used to manage both of the out-of-mainline and in-mainline features.

```
1 $ make feature-list
2 [ /labs/linux-lab/src/feature/linux ]:
3 + 9pnet
4 + core
5   - debug
6   - module
7 + ftrace
8   - v2.6.36
9     * env.g3beige
10    * env.malta
11    * env.pc
12    * env.versatilepb
13   - v2.6.37
14    * env.g3beige
15 + gcs
16   - v2.6.36
17     * env.g3beige
18     * env.malta
19     * env.pc
20     * env.versatilepb
21 + kft
22   - v2.6.36
23     * env.malta
24     * env.pc
25 + uksm
26   - v2.6.38
```

Verified boards and Linux versions are recorded there, so, it should work without any issue if the environment not changed.

4.1.3.2 using kernel modules

For example, to enable kernel modules support, simply do:

```
1 // only upper case 'FEATURE' will be saved
2 $ make feature FEATURE=module
3 $ make kernel-olddefconfig
4 $ make kernel
```

4.1.3.3 using rust feature

Use `x86_64/pc` as an example:

```
1 $ make BOARD=x86_64/pc
```

switch to v6.1.1 Linux:

```
1 $ make config LINUX=v6.1.1
```

Compile the kernel, and test it with one of the simplest module - `rust_minimal`:

```
1 // clean up everything for a whole new test
2 $ make kernel-cleanall
3
4 // this 'f' variable will not be saved for standalone make targets
5 $ make test f=rust m=rust_minimal
```

4.1.3.4 using kft feature

For `kft` feature in v2.6.36 for malta board:

```
1 $ make cleanall b=malta
2 $ make test b=malta f=kft LINUX=v2.6.36
```

4.1.3.5 using rt feature

Linux officially provide RT Preemption support, but many patches are outside of mainline kernel, to use it:

```
1 $ make feature-list f=rt
2 $ make test b=i386/pc f=rt LINUX=v5.2
```

4.1.3.6 persist or clear feature setting

Clear feature setting (reset feature saved in `.labconfig`):

```
1 $ make feature FEATURE=rust
2 $ make feature FEATURE=
```

The above function is the same as 'make config'.

4.1.4 Create new development branch

If want to use a new development branch, please follow such steps:

At first, Get into `src/linux-stable` or another directory specified with `KERNEL_SRC`, checkout a development branch from a specific version:

```
1 $ cd src/linux-stable
2 $ git checkout -b linux-v5.1-dev v5.1
```

And then, clone the necessary configurations and directories for our new branch.

```
1 $ make kernel-clone LINUX=v5.1 LINUX_NEW=linux-v5.1-dev
```

The v5.1 must be the already supported version, if not, please use the near one in supported list, for example, `i386/pc` board support such versions:

```
1 $ make b=i386/pc list linux
2 v2.6.10 v2.6.11.12 v2.6.12.6 v2.6.21.5 v2.6.24.7 v2.6.34.9 v2.6.35.14 v2.6.36 v4.6.7 [v5
   .1] v5.2
```

If want to develop v2.6.38, please try to clone one from v2.6.36:

```
1 $ cd src/linux-stable
2 $ git checkout -b linux-v2.6.38-dev v2.6.38
3 $ make kernel-clone LINUX=v2.6.36 LINUX_NEW=linux-v2.6.38-dev
```

In development, please commit asap, and also, please use such commands carefully to avoid destroy your important changes:

- kernel-checkout, checkout a specified kernel version, may override your changes
- kernel-cleanup, clean up git repository, may remove your changes
- kernel-clean, clean building history
- kernel-cleanall, clean both of the building history and the source code changes

4.1.5 Use standalone git repository

v0.8 starts to add `KERNEL_FORK`, allows to configure the third party Linux source code repository, has added openEuler and wsl2, both of them support `x86_64/pc` and the former support `aarch64/virt` too.

For example, to compile wsl2 kernel, switch `KERNEL_FORK` to wsl2 directly:

```
1 $ make BOARD=x86_64/pc
2 $ make config KERNEL_FORK=wsl2
3 $ make kernel
```

To configure the wsl2 kernel version, configure it as following:

```
1 $ make edit
2 LINUX[KERNEL_FORK_wsl2] := linux-msft-wsl-5.10.74.3
```

The value should be one of the available tag in `git tag` list.

4.2 Using U-Boot Bootloader

Choose one of the tested boards: `versatilepb` and `vexpress-a9`.

```
1 $ make BOARD=vexpress-a9
```

Download Uboot:

```
1 $ make uboot-source
```

Checkout the specified version:

```
1 $ make uboot-checkout
```

Patching with necessary changes, `BOOTDEV` and `ROOTDEV` available, use `flash` by default.

```
1 $ make uboot-patch
```

Use `tftp`, `sdcard` OR `flash` explicitly, should run `make U-Boot-checkout` before a new `uboot-patch`:

```
1 $ make uboot-patch BOOTDEV=tftp
2 $ make uboot-patch BOOTDEV=sdcard
3 $ make uboot-patch BOOTDEV=flash
```

`BOOTDEV` is used to specify where to store and load the images for `uboot`, `ROOTDEV` is used to tell kernel where to load the rootfs.

Configure:

```
1 $ make uboot-defconfig
2 $ make uboot-menuconfig
```

Building:

```
1 $ make uboot
```

Boot with `BOOTDEV` and `ROOTDEV`, use `flash` by default:

```
1 $ make boot U=1
```

Use `tftp`, `sdcard` OR `flash` explicitly:

```
1 $ make boot U=1 BOOTDEV=tftp
2 $ make boot U=1 BOOTDEV=sdcard
3 $ make boot U=1 BOOTDEV=flash
```

We can also change `ROOTDEV` during boot, for example:

```
1 $ make boot U=1 BOOTDEV=flash ROOTDEV=nfs
```

Clean images if want to update `ramdisk`, `dtb` and `uImage`:

```
1 $ make uboot-images-clean
2 $ make uboot-clean
```

Save U-Boot images and configs:

```
1 $ make uboot-save
2 $ make uboot-saveconfig
```

4.3 Using QEMU Emulator

Builtin QEMU may not work with the newest Linux kernel, so, we need compile and add external prebuilt qemu, this has been tested on vexpress-a9 and virt board.

At first, build qemu-system-ARCH:

```
1 $ make B=vexpress-a9
2 $ make qemu
3 $ make qemu-save
```

QEMU-ARCH-static and qemu-system-ARCH can not be compiled together. to build QEMU-ARCH-static, please enable `QEMU_US=1` in board specific Makefile and rebuild it.

If QEMU and QTOOL specified, the one in bsp submodule will be used in advance of one installed in system, but the first used is the one just compiled if exists.

While porting to newer kernel, Linux 5.0 hangs during boot on QEMU 2.5, after compiling a newer QEMU 2.12.0, no hang exists. please take notice of such issue in the future kernel upgrade.

If already download QEMU and its submodules and don't want to upadte the submodules, just skip it:

```
1 $ make qemu git_module_status=0
```

4.4 Using Toolchains

The pace of Linux mainline is very fast, builtin toolchains can not keep up, to reduce the maintaining pressure, external toolchain feature is added. for example, ARM64/virt, CCVER and CCPATH has been added for it.

List available prebuilt toolchains:

```
1 $ make gcc-list
```

Download, decompress and enable the external toolchain:

```
1 $ make gcc
```

Switch compiler version if exists, for example:

```
1 $ make gcc-switch CCORI=internal GCC=4.8
2
3 $ make gcc-switch CCORI=linaro
```

If not external toolchain there, the builtin will be used back.

If no builtin toolchain exists, please must use this external toolchain feature, currently, aarch64, arm, riscv, mipsel, ppc, i386, x86_64 support such feature.

GCC version can be configured in board specific Makefile for Linux, Uboot, Qemu and Root, for example:

```
1 GCC[LINUX_v2.6.11.12] = 4.4
```

With this configuration, GCC will be switched automatically during defconfig and compiling of the specified Linux v2.6.11.12.

To build host tools, host gcc should be configured too(please specify b=i386/pc explicitly):

```
1 $ make gcc-list b=i386/pc
2 $ make gcc-switch CCORl=internal GCC=4.8 b=i386/pc
```

4.5 Using Rootfs

Builtin rootfs is minimal, is not enough for complex application development, which requires modern Linux distributions.

Such a type of rootfs has been introduced and has been released as docker image, ubuntu 18.04 is added for arm32v7 at first, more later.

Run it via docker directly:

```
1 $ docker run -it tinylab/arm32v7-ubuntu
```

Extract it out and run in Linux Lab:

```
1 (host)$ sudo apt-get install -y qemu-user-static
```

ARM32/vexpress-a9 (user: root, password: root):

```
1 (host)$ tools/root/docker/extract.sh tinylab/arm32v7-ubuntu arm
2 (lab )$ make boot b=arm/vexpress-a9 U=0 V=1 MEM=1024M ROOTDEV=nfs ROOTFS=$PWD/prebuilt/
    fullroot/tmp/tinylab-arm32v7-ubuntu
```

ARM64/raspi3 (user: root, password: root):

```
1 (host)$ tools/root/docker/extract.sh tinylab/arm64v8-ubuntu arm
2 (lab )$ make boot b=aarch64/virt V=1 ROOTDEV=nfs ROOTFS=$PWD/prebuilt/fullroot/tmp/
    tinylab-arm64v8-ubuntu
```

More rootfs from docker can be found:

```
1 $ docker search arm64 | egrep "ubuntu|debian"
2 arm64v8/ubuntu  Ubuntu is a Debian-based Linux operating system 25
3 arm64v8/debian  Debian is a Linux distribution that's composed 20
```

4.6 Debugging Linux and U-Boot

4.6.1 Debugging Linux

Compile the kernel with debugging options:

```
1 $ make feature FEATURE=debug
2 $ make kernel-olddefconfig
3 $ make kernel
```

Compile with one thread:

```
1 $ make kernel JOBS=1
```

And then debug it directly:

```
1 $ make debug
```

The above command will use tmux to split into two terminals, each running QEMU and gdb respectively, and load the script from `.gdb/kernel.default`.

To switch tmux panes, use CTRL+b followed by the arrow key (e.g., ←).

To customize kernel gdbinit script, simply copy one and edit it manually:

```
1 $ cp .gdb/kernel.default .gdb/kernel.user
```

It equals to:

```
1 $ make debug linux
```

to automate debug testing:

```
1 $ make test-debug linux
```

find out the code line of a kernel panic address:

```
1 $ make kernel-calltrace func+offset/length
```

if the debug port has been used, please try to find out who used the port and kill it:

```
1 $ sudo netstat -tlnp | grep 1234
2 tcp        0      0 0.0.0.0:1234          0.0.0.0:*           LISTEN          3943/qemu-
   xxx
3 $ sudo kill -9 3943
```

4.6.2 Debugging U-Boot

To debug U-Boot with `.gdb/uboot.default`:

```
1 $ make debug uboot
```

The above command will use tmux to split into two terminals, each running QEMU and gdb respectively.

To switch tmux panes, use CTRL+b followed by the arrow key (e.g., ←).

To automate U-Boot debug testing:

```
1 $ make test-debug uboot
```

The same to kernel gdbinit script, customize one for uboot:

```
1 $ cp .gdb/uboot.default .gdb/uboot.user
```

4.7 Test Automation

Use aarch64/virt as the demo board here.

```
1 $ make BOARD=virt
```

Prepare for testing, install necessary files/scripts in `src/system/`:

```
1 $ make rootdir
2 $ make root-rebuild
```

Simply boot and poweroff (See [poweroff hang](#)):

```
1 $ make test
```

Don't poweroff after testing:

```
1 $ make test TEST_FINISH=echo
```

Run guest test case:

```
1 $ make test TEST_CASE=/tools/ftrace/trace.sh
```

Run guest test cases (`COMMAND_LINE_SIZE` must be big enough, e.g. 4096, see `cmdline_size` feature below):

```
1 $ make test TEST_BEGIN=date TEST_END=date TEST_CASE='ls /;echo hello world'
```

Reboot the guest system for several times:

```
1 $ make test TEST_REBOOT=2
```

NOTE: reboot may 1) hang, 2) continue; 3) timeout killed, `TEST_TIMEOUT=30`;
4) timeout continue, `TIMEOUT_CONTINUE=1`

Test a feature of a specified Linux version on a specified board (`cmdline_size` feature is for increase `COMMAND_LINE_SIZE` to 4096):

```
1 $ make test f=kft LINUX=v2.6.36 b=malta TEST_PREPARE=board-init,kernel-cleanup
```

NOTE: `board-init` and `kernel-cleanup` make sure test run automatically, but `kernel-cleanup` is not safe, please save your code before use it!!

Test a kernel module:

```
1 $ make test m=hello
```

Test multiple kernel modules:

```
1 $ make test m=exception,hello
```

Test modules with specified ROOTDEV, `nfs` boot is used by default, but some boards may not support network:

```
1 $ make test m=hello,exception TEST_RD=ram0
```

Run test cases while testing kernel modules (test cases run between `insmod` and `rmmod`):

```
1 $ make test m=exception TEST_BEGIN=date TEST_END=date TEST_CASE='ls /root;echo hello world' TEST_PREPARE=board-init,kernel-cleanup f=cmdline_size
```

Run test cases while testing internal kernel modules:

```
1 $ make kernel-setconfig y=debug_fs
2 $ make test m=lkdtm TEST_BEGIN='mount -t debugfs debugfs /mnt' TEST_CASE='echo EXCEPTION > /mnt/provoke-crash/DIRECT'
```

Run test cases while testing internal kernel modules, pass kernel arguments:

```
1 $ make test m=lkdtm lkdtm_args='cpoint_name=DIRECT cpoint_type=EXCEPTION'
```

Run test without `feature-init` (save time if not necessary):

```
1 $ make test m=lkdtm lkdtm_args='cpoint_name=DIRECT cpoint_type=EXCEPTION' TEST_INIT=0
2 Or
3 $ make raw-test m=lkdtm lkdtm_args='cpoint_name=DIRECT cpoint_type=EXCEPTION'
```

Run test with module and the module's necessary dependencies (check with `make kernel-menuconfig`):

```
1 $ make test m=lkdtm y=runtime_testing_menu,debug_fs lkdtm_args='cpoint_name=DIRECT cpoint_type=EXCEPTION' LINUX=v5.1 TEST_PREPARE=kernel-cleanup
```

Run test without `feature-init`, `boot-init`, `boot-finish` and no `TEST_PREPARE`:

```
1 $ make boot-test m=lkdtm lkdtm_args='cpoint_name=DIRECT cpoint_type=EXCEPTION'
```

Test a kernel module and make some targets before testing:

```
1 $ make test m=exception TEST=kernel-checkout,kernel-patch,kernel-defconfig
```

Test everything in one command (from download to poweroff, see [poweroff hang](#)):

```
1 $ make test TEST=kernel,root TEST_PREPARE=board-init,kernel-cleanup,root-cleanup
```

Test everything in one command (with U-Boot while support, e.g. vexpress-a9):

```
1 $ make test TEST=kernel,root,uboot TEST_PREPARE=board-init,kernel-cleanup,root-cleanup,
  uboot-cleanup
```

Test kernel hang during boot, allow to specify a timeout, timeout must happen while system hang:

```
1 $ make test TEST_TIMEOUT=30s
```

Test kernel debug:

```
1 $ make test DEBUG=1
```

Notes: The above tests may fail on some boards with some Linux versions, please upgrade the kernel versions if necessary.

4.8 File Sharing

To transfer files between QEMU Board and Host, three methods are supported by default:

4.8.1 Install files to rootfs

Simply put the files with a relative path in `src/system/`, install and rebuild the rootfs:

```
1 $ mkdir src/system/root/
2 $ touch src/system/root/new_file
3 $ make root-rebuild
4 $ make boot
```

4.8.2 Share with NFS

Boot the board with `ROOTDEV=nfs`:

```
1 $ make boot ROOTDEV=nfs
```

Host:

```
1 $ make env-dump VAR=ROOTDIR
2 ROOTDIR="/labs/linux-lab/boards/<BOARD>/bsp/root/<BUILDROOT_VERSION>/rootfs"
```

4.8.3 Transfer via tftp

Using tftp server of host from the QEMU board with the `tftp` command.

Host:

```
1 $ ifconfig br0
2 inet addr:172.17.0.3 Bcast:172.17.255.255 Mask:255.255.0.0
3 $ cd tftpboot/
4 $ ls tftpboot
5 kft.patch kft.log
```

QEMU Board:

```
1 $ ls
2 kft_data.log
3 $ tftp -g -r kft.patch 172.17.0.3
4 $ tftp -p -r kft.log -l kft_data.log 172.17.0.3
```

Note: while put file from QEMU board to host, must create an empty file in host firstly. Buggy?

4.8.4 Share with 9p virtio

To enable 9p virtio for a new board, please refer to [qemu 9p setup](#). qemu must be compiled with `--enable-virtfs`, and kernel must enable the necessary options.

Reconfigure the kernel with:

```
1 CONFIG_NET_9P=y
2 CONFIG_NET_9P_VIRTIO=y
3 CONFIG_NET_9P_DEBUG=y (Optional)
4 CONFIG_9P_FS=y
5 CONFIG_9P_FS_POSIX_ACL=y
6 CONFIG_PCI=y
7 CONFIG_VIRTIO_PCI=y
8 CONFIG_PCI_HOST_GENERIC=y (only needed for the QEMU Arm 'virt' board)
```

If using `-virtfs` OR `-device virtio-9p-pci` option for qemu, must enable the above PCI related options, otherwise will not work:

```
1 9pnet_virtio: no channels available for device hostshare
2 mount: mounting hostshare on /hostshare failed: No such file or directory
```

`-device virtio-9p-device` requires less kernel options.

To enable the above options, please simply type:

```
1 $ make feature FEATURE=9pnet
2 $ make kernel-olddefconfig
```

Docker host:

```
1 $ modprobe 9pnet_virtio
2 $ lsmod | grep 9p
3 9pnet_virtio          17519  0
4 9pnet                 72068  1 9pnet_virtio
```

Host:

```
1 $ make BOARD=virt
2
3 $ make root-rebuild
4
5 $ touch hostshare/test # Create a file in host
6
7 $ make boot U=0 ROOTDEV=ram0 PBR=1 SHARE=1
8
9 $ make boot SHARE=1 SHARE_DIR=src/modules # for external modules development
10
11 $ make boot SHARE=1 SHARE_DIR=build/aarch64/linux-v5.1-virt/ # for internal modules
    learning
12
13 $ make boot SHARE=1 SHARE_DIR=src/examples # for c/assembly learning
```

QEMU Board:

```
1 $ ls /hostshare/ # Access the file in guest
2 test
3 $ touch /hostshare/guest-test # Create a file in guest
```

Verified boards with Linux v5.1:

boards	Status
aarch64/virt	virtio-9p-device (virtio-9p-pci breaks nfsroot)
arm/vexpress-a9	only work with virtio-9p-device and without U-Boot booting
arm/versatilepb	only work with virtio-9p-pci
x86_64/pc	only work with virtio-9p-pci
i386/pc	only work with virtio-9p-pci
riscv64/virt	work with virtio-9p-pci and virtio-9p-dev
riscv32/virt	work with virtio-9p-pci and virtio-9p-dev

4.9 Learning Assembly

Linux Lab has added many assembly examples in `src/examples/assembly`:

```
1 $ cd src/examples/assembly
2 $ ls
3 aarch64 arm mips64el mipsel powerpc powerpc64 riscv32 riscv64 x86 x86_64
4 $ make -s -C aarch64/
5 Hello, ARM64!
```

4.10 Learning C

4.10.1 Host build and Run

Use hello as example:

```
1 $ cd src/examples/c/hello
2 $ make
3 gcc -fno-stack-protector -fomit-frame-pointer -fno-asynchronous-unwind-tables -fno-pie -
   no-pie -m32 -Wall -Werror -g -o hello hello.c
4 Hello, World!
```

4.10.2 Cross build and Run

Use X32 (Code for x86-64, int/long/pointer to 32bits), ARM, MIPS, PPC and RISC-V as example:

```
1 $ sudo apt-get update -y
2
3 $ sudo apt-get install -y libc6-x32 libc6-dev-x32 libx32gcc-8-dev
4 $ gcc -mx32 -o hello hello.c
5 $ ./hello
6 Hello, World!
7
8 $ sudo apt-get install -y libc6-dev-armel-cross libc6-armel-cross
9 $ arm-linux-gnueabi-gcc -o hello hello.c
10 $ qemu-arm -L /usr/arm-linux-gnueabi/ ./hello
11 Hello, World!
12
13 $ sudo apt-get install -y libc6-dev-mipsel-cross libc6-mipsel-cross
14 $ mipsel-linux-gnu-gcc -o hello hello.c
15 $ qemu-mipsel -L /usr/mipsel-linux-gnu/ ./hello
16 Hello, World!
17
18 $ sudo apt-get install -y libc6-dev-powerpc-cross libc6-powerpc-cross
19 // Must use -static for Linux Lab v0.6, otherwise, there will be segmentation fault
20 $ powerpc-linux-gnu-gcc -static -o hello hello.c
21 $ qemu-ppc -L /usr/powerpc-linux-gnu/ ./hello
22 Hello, World!
23
24 $ sudo apt-get install -y libc6-riscv64-cross libc6-dev-riscv64-cross
25 $ riscv64-linux-gnu-gcc -o hello hello.c
26 $ qemu-riscv64 -L /usr/riscv64-linux-gnu/ ./hello
27 Hello, World!
```

Above run through `qemu-user`, to run on target boards, please copy the binaries to target boards' rootfs with help from section 4.8.1.

The main packages are `libc6-dev`, `libc6` or `libgcc`, but `x32` is an exception, it is `libx32gcc`. please list them via `apt-cache search`.

4.11 Running any make goals

Linux Lab allows to access Makefile goals of the APPS easily, for example:

```
1 $ make kernel help
2 $ make kernel menuconfig
3
4 $ make root help
5 $ make root busybox-menuconfig
6
7 $ make uboot help
8 $ make uboot menuconfig
9
10 Or
11
12 $ make kernel-help
13 $ make kernel-menuconfig
14
15 $ make root-help
16 $ make root-busybox-menuconfig
17
18 $ make uboot-help
19 $ make uboot-menuconfig
```

Allows to run sub-make goals of kernel, root and U-Boot directly without entering into their own building directory.

4.12 Speed up kernel development

4.12.1 Speed up compiling and save disk life

Notes : This operation may lose data, please take care!

This feature aims to create a ram based temporary filesystem as the 'build' directory, to store the building data, **If not backup them, they will be lost after shutting down the machine.**

Create temporary building cache:

```
1 $ make build cache
```

Check the status of building cache:

```
1 $ make build status
```

Use the cache for building speedup:

```
1 $ time make kernel
```

Backup the cache to a persistent file (If the building file are important to you):

```
1 $ make build backup
```

Stop the building cache, revert back to use the build directory on the disk:

```
1 $ make build uncache
```

Use the backup as the build directory:

```
1 $ sudo mount /path/to/backup-file /labs/linux-lab/build/
```

4.12.2 ONESHOT Mode

v0.9 adds a `ONESHOT` switch, it can be used to enable such functions:

- Auto cache `build/` in memory
- Auto cache `src/` in memory
- Auto enable fast fetch, a.k.a git shallow fetch

It is good for:

- Disposable, destroy after using
 - If want, please save kernel and its config with `kernel-save` and `kernel-saveconfig`
- Better for big-memory, small-disk and slow-CPU host machines
 - Both `src/` and `build/` are put in memory, not in disk
- Good for instant kernel downloading and building
 - If target host has no Linux kernel source code, and the network is slow

To use it, please simply run this before others:

```
1 $ export ONESHOT=1
```

If want to make it persistent, just configure it in `.labinit`:

```
1 ONESHOT := 1
```

4.12.3 Nolibc Mode

v1.2-rc2 adds Nolibc mode, allows to build ultra small kernel and application, and package them together via `initrd`, to achieve “Kernel-only” deployments.

Nolibc adds two types of files:

- Small kernel config file: `boards/<ARCH>/<BOARD>/bsp/configs/linux_v6.x_nolibc_defconfig`

- Small nolibc application: `src/examples/nolibc/hello.c`

Just similar to `ONESHOT`, before developing, just run this to enable `NOLIBC` mode:

```
1 $ export NOLIBC=1
```

Or, write to `.labinit` to let it always work:

```
1 NOLIBC := 1
```

To change the target nolibc application, we can configure `NOLIBC_SRC`, otherwise, the above `hello.c` will be used by default:

```
1 $ make nolibc-clean
2 $ make kernel NOLIBC_SRC=$PWD/src/examples/nolibc/hello.c
```

It is very good for pure kernel development.

4.12.4 Tiny Mode

Based on Nolibc mode, v1.4-rc2 adds Tiny mode, allows to build ultra small kernel but with `initrd` boot support.

Usage:

```
1 $ export KCFG=linux.tiny.config
2 $ make kernel
3 $ make boot ROOTDEV=ram0
```

Compare to `defconfig`, it only enables minimal config options and makes sure `initrd` boot with an interactive shell, so, the compiling speed is x10 faster.

It is very good for kernel features testing, development and research.

4.13 More Usage

Read more:

- Why
 - [Why Using Linux Lab V1.0 \(In Chinese\)](#)
 - [Why Using Linux Lab V2.0 \(In Chinese\)](#)
- User Manual
 - [Linux Lab v1.4 User Manual](#)
 - [Linux Lab v1.3 User Manual](#)
 - [Linux Lab v1.2 User Manual](#)

- [Linux Lab v1.1 User Manual](#)
- [Linux Lab v1.0 User Manual](#)
- [Linux Lab v0.9 User Manual](#)
- [Linux Lab v0.8 User Manual](#)
- [Linux Lab Loongson Manual V0.2](#)
- Linux Lab Videos
 - [CCTALK](#)
 - [Bilibili](#)
- Video Courses use Linux Lab as experiment environment
 - [The Perspective Linux ELF](#)
 - [《Rust Language Quickstart》](#)
 - [《Software Reverse Engineering Quickstart》](#)
 - [《Linux Kernel Livepatch Introduction》](#)
- The books or courses Linux Lab supported or plan to support
 - [books or courses list](#)
- The boards Linux Lab supported or plan to support
 - [ARM IMX6ULL](#)
 - [RISCV-64 D1](#)
- The hardwares developed by Linux Lab community
 - [Linux Lab Disk](#), pre-installed Linux Lab disk
 - * Support Ubuntu 18.04-21.04, Deepin 20.2+, Fedora 34+, Mint 20.2+, Ezgo 14.04+, Kali, Manjaro
 - [Pocket Linux Disk](#), pre-installed Linux distribution disk
 - * Support Ubuntu 18.04-21.04, Deepin 20.2+, Fedora 34+, Mint 20.2+, Ezgo 14.04+, Kali, Manjaro

5. Linux Lab Development

This introduces how to add a new board for Linux Lab.

5.1 Choose a board supported by QEMU

list the boards, use arm as an example:

```
1 $ qemu-system-arm -M ?
```

5.2 Create the board directory

Use `vexpress-a9` as an example:

```
1 $ mkdir boards/arm/vexpress-a9/
```

5.3 Clone a Makefile from an existing board

Use `versatilepb` as an example:

```
1 $ cp boards/arm/versatilepb/Makefile boards/arm/vexpress-a9/Makefile
```

5.4 Configure the variables from scratch

Comment everything, add minimal ones and then others.

Please refer to `doc/qemu/qemu-doc.html` or the online one <https://www.qemu.org/docs/master/>.

5.5 At the same time, prepare the configs

We need to prepare the configs for linux, buildroot and even uboot.

Buildroot has provided many examples about buildroot and kernel configuration:

```
1 buildroot: src/buildroot/configs/qemu_ARCH_BOARD_defconfig
2 kernel: src/buildroot/board/qemu/ARCH-BOARD/linux-VERSION.config
```

U-Boot has also provided many default configs:

```
1 uboot: src/u-boot/configs/vexpress_ca9x4_defconfig
```

Kernel itself also:

```
1 kernel: src/linux-stable/arch/arm/configs/vexpress_defconfig
```

Linux Lab itself also provide many working configs too, the `xxx-clone` target is a good helper to utilize existing configs:

```
1 $ make list kernel
2 v4.12 v5.0.10 v5.1
3 $ make kernel-clone LINUX=v5.1 LINUX_NEW=v5.4
4 $ make kernel-menuconfig
5 $ make kernel-saveconfig
6
7 $ make list root
8 2016.05 2019.02.2
9 $ make root-clone BUILDROOT=2019.02.2 BUILDROOT_NEW=2019.11
10 $ make root-menuconfig
11 $ make root-saveconfig
```

Edit the configs and Makefile until they match our requirements.

```
1 $ make kernel-menuconfig
2 $ make root-menuconfig
3 $ make board-edit
```

The configuration must be put in `boards/<BOARD>/` and named with necessary version info, use `raspi3` as an example:

```
1 $ make kernel-saveconfig
2 $ make root-saveconfig
3 $ ls boards/aarch64/raspi3/bsp/configs/
4 buildroot_2019.02.2_defconfig linux_v5.1_defconfig
```

2019.02.2 is the buildroot version, v5.1 is the kernel version, both of these variables should be configured in `boards/<BOARD>/Makefile`.

More usage about the `xxx-clone` commands:

```
1 $ make qemu-clone QEMU=<old_version> QEMU_NEW=<new_version>
2 $ make uboot-clone UBOOT=<old_version> UBOOT_NEW=<new_version>
3 $ make kernel-clone LINUX=<old_version> LINUX_NEW=<new_version>
4 $ make root-clone BUILDROOT=<old_version> BUILDROOT_NEW=<new_version>
```

5.6 Choose the versions of kernel, rootfs and U-Boot

Please use `tag` instead of `branch`, use `kernel` as an example:

```
1 $ cd src/linux-stable
2 $ git tag
3 ...
4 v5.0
5 ...
6 v5.1
7 ..
8 v5.1.1
9 v5.1.5
10 ...
```

If want v5.1 kernel, just put a line “LINUX = v5.1” in boards/<BOARD>/Makefile.

Or clone a kernel config from the old one or the official defconfig:

```
1 $ make kernel-clone LINUX_NEW=v5.3 LINUX=v5.1
2
3 Or
4
5 $ make B=i386/pc
6 $ pushd Linux-stable && git checkout v5.4 && popd
7 $ make kernel-clone LINUX_NEW=v5.4 KCFG=i386_defconfig
```

If no tag existed, a virtual tag name with the real commit number can be configured as following:

```
1 LINUX = v2.6.11.12
2 LINUX[LINUX_v2.6.11.12] = 8e63197f
```

Linux version specific ROOTFS are also supported:

```
1 ROOTFS[LINUX_v2.6.12.6] ?= $(BSP_ROOT)/$(BUILDR00T)/rootfs32.cpio.gz
```

5.7 Configure, build and boot them

Use kernel as an example:

```
1 $ make kernel-defconfig
2 $ make kernel-menuconfig
3 $ make kernel
4 $ make boot
```

The same to Rootfs, U-Boot and even QEMU.

5.8 Save the images and configs

```
1 $ make root-save
2 $ make kernel-save
3 $ make uboot-save
4
5 $ make root-saveconfig
6 $ make kernel-saveconfig
7 $ make uboot-saveconfig
```

5.9 Upload everything

At last, upload the images, defconfigs, patchset to board specific bsp submodule repository.

Firstly, get the remote bsp repository address as following:

```
1 $ git remote show origin
2 * remote origin
3   Fetch URL: https://gitee.com/tinylab/qemu-aarch64-raspi3/
4   Push URL: https://gitee.com/tinylab/qemu-aarch64-raspi3/
5   HEAD branch: master
6   Remote branch:
7     master tracked
8   Local branch configured for 'git pull':
9     master merges with remote master
10  Local ref configured for 'git push':
11  master pushes to master (local out of date)
```

Then, fork this repository from gitee.com, upload your changes, and send your pull request.

6. FAQs

6.1 Docker Issues

6.1.1 Speed up docker images downloading

To optimize docker images download speed, please refer to section 6.1.6.

6.1.2 Docker network conflicts with LAN

Cloud Lab use a default 172.20.0.0/16 subnet, if this conflicts with another one, please change it like this:

```
1 $ tools/docker/rm-all
2 $ vim configs/linux-lab/docker/subnet
3 $ cat configs/linux-lab/docker/subnet
4 172.23.0.0/16
5 $ tools/docker/run linux-lab
```

If lab network still not work, please try another private network address and eventually to avoid conflicts with LAN address.

6.1.3 Why not allow running Linux Lab in local host

The full function of Linux Lab depends on the full docker environment managed by [Cloud Lab](#), so, please really never try and therefore please don't complain about why there are lots of packages missing failures and even the other weird issues.

Linux Lab is designed to use pre-installed environment with the docker technology and save our life by avoiding the packages installation issues in different systems, so, Linux Lab would never support local host using even in the future.

6.1.4 Run tools without sudo

To use the tools under `tools` without `sudo`, please make sure add your account to the docker group and reboot your system to take effect:

```
1 $ sudo usermod -aG docker <USER>
2 $ newgrp docker
```

If get error: “newgrp: group ‘docker’ does not exist”, please add ‘docker’ group manually:

```
1 $ sudo groupadd docker
```

Notes: Currently, root user is not allowed to run Linux Lab.

6.1.5 Network not work

If ping not work, please check one by one:

- DNS issue

if ping 8.8.8.8 work, please check `/etc/resolv.conf` and make sure it is the same as your host configuration.

- IP issue

if ping not work, please refer to [network conflict issue](#) and change the ip range of docker containers.

6.1.6 Client.Timeout exceeded while waiting headers

This means must configure one of the following docker mirror sites:

- [Aliyun Docker Mirror Documentation](#)
- [USTC Docker Mirror Documentation](#)

Potential methods of configuration in Ubuntu, depends on docker and Ubuntu versions:

`/etc/default/docker:`

```
1 echo "DOCKER_OPTS=\"\${DOCKER_OPTS} --registry-mirror=<your accelerate address>\""
```

`/lib/systemd/system/docker.service:`

```
1 ExecStart=/usr/bin/dockerd -H fd:// --registry-mirror=<your accelerate address>
```

`/etc/docker/daemon.json:`

```
1 {
2   "registry-mirrors": ["<your accelerate address>"]
3 }
```

Please restart docker service after change the accelerate address:

```
1 $ sudo service docker restart
```

For the other Linux systems, Windows and macOS System, please refer to [Aliyun Mirror Speedup Document](#).

IF still slow, please check if the mirror site is configured normally and without typos:

```
1 $ docker info | grep -A1 -i Mirrors
2 Registry Mirrors:
3   https://XXXXX.mirror.aliyuncs.com/
```

6.1.7 Restart Linux Lab after host system shutdown or reboot

If want to restore the installed softwares and related configurations, please save the container manually:

```
1 $ tools/docker/save linux-lab
```

After host system (include virtual machine) shutdown or reboot, you can restart the lab via the “Linux Lab” icon on the desktop, or just like before, issue this command:

```
1 $ tools/docker/run linux-lab
```

Current implementation doesn't support the direct ‘docker start’ command, please learn it.

If the above methods still not restart the lab, please refer to the methods mentioned in the 6.3.9 section.

If resume from a suspended host system, the lab will restore automatically, no need to do anything to restart it, just use one of the 4 login methods mentioned in the 2.4 section, for example, start a web browser to connect it:

```
1 $ tools/docker/webvnc
```

6.1.8 the following directives are specified both as a flag and in the configuration file

If getting such error:

```
1 unable to configure the Docker daemon with file /etc/docker/daemon.json: the
2 following directives are specified both as a flag and in the configuration
3 file: registry-mirrors: (from flag: [https://docker.mirrors.ustc.edu.cn/], from
4 file: [https://xxx.mirror.aliyuncs.com])
```

Means both `/etc/docker/daemon.json` and `/etc/default/docker` configured `registry-mirrors`, please comment the late one and restart docker:

```
1 $ sudo service docker restart
```

6.1.9 pathspec FETCH_HEAD did not match any file known to git

If get such error while running `make boot`, it means network issue, please refer to section 6.1.5。

```
1 Could not resolve host: gitee.com
2 error: pathspec 'FETCH_HEAD' did not match any file(s) known to git
```

6.1.10 Docker not work in Ubuntu 20.04

If docker not work in Ubuntu 20.04, please use `doc/install/daemon.json` and clean up the arguments of `dockerd`, learn more from [docker daemon](#):

```
1 $ sudo cat /etc/systemd/system/docker.service.d/docker.conf
2 [Service]
3 ExecStart=
4 ExecStart=/usr/bin/dockerd
5
6 $ sudo cp /etc/docker/daemon.json /etc/docker/daemon.json.bak
7 $ sudo cp doc/install/daemon.json /etc/docker/
8 $ sudo service docker restart
```

Please make sure using the best `registry-mirrors` for better download speed.

6.1.11 Error creating aufs mount

If not work with failure like “error creating aufs mount to ... invalid arguments”, that means the storage driver used by docker is not supported by current system, please choose another one from [this page](#), and configure it in `/etc/docker/daemon.json`, for example:

```
1 $ sudo vim /etc/docker/daemon.json
2 {
3   "registry-mirrors": ["https://docker.mirrors.ustc.edu.cn"],
4   "storage-driver": "devicemapper"
5 }
```

This issue is related to kernel version, the same system may upgrade kernel version and therefore support different storage driver.

6.2 QEMU Issues

6.2.1 Why kvm speeding up is disabled

kvm only supports both of `qemu-system-i386` and `qemu-system-x86_64` currently, and it also requires the CPU and bios support, otherwise, you may get this error log:

```
1 modprobe: ERROR: could not insert 'kvm_intel': Operation not supported
```

Check CPU virtualization support, if nothing output, then, cpu not support virtualization:

```
1 $ cat /proc/cpuinfo | egrep --color=always "vmx|svm"
```

If CPU supports, we also need to make sure it is enabled in bios features, simply reboot your computer, press ‘Delete’ to enter bios, please make sure the ‘Intel virtualization technology’ feature is ‘enabled’.

6.2.2 Poweroff hang

Both of the `poweroff` and `reboot` commands not work on these boards currently (LINUX=v5.1):

- mipsel/malta (exclude LINUX=v2.6.36)
- mipsel/ls232
- mipsel/ls1b
- mips64el/ls2k
- mips64el/ls3a7a
- aarch64/raspi3
- arm/versatilepb

System will directly hang there while running `poweroff` or `reboot`, to exit qemu, please pressing `CTRL+a x` OR using `pkill qemu`.

To test such boards automatically, please make sure setting `TEST_TIMEOUT`, e.g. `make test TEST_TIMEOUT=50`.

Welcome to fix up them.

6.2.3 How to exit QEMU

Where	How
Serial Port Console	<code>CTRL+a x</code>
Curses based Graphic	<code>ESC+2 quit</code> OR <code>ALT+2 quit</code>
X based Graphic	<code>CTRL+ALT+2 quit</code>
Generic Methods	<code>poweroff, reboot, kill, pkill</code>

6.2.4 Boot with missing sdl2 libraries failure

That's because the docker image is not updated, just enter into cloud-lab and rerun the lab (please must not use `tools/docker/restart` here for it not using the new docker image):

```
1 $ tools/docker/rerun linux-lab
```

6.3 Environment Issues

6.3.1 NFS/tftpboot not work

If nfs or tftpboot not work, please run `modprobe nfsd` in host side and restart the net services via `/configs/tools/restart-net-servers.sh` in guest side and please make sure not use `tools/docker/trun`.

6.3.2 How to switch Windows in VIM

`CTRL+w` is used in both of browser and vim, to switch from one window to another, please USE `CTRL+Left` OR `CTRL+Right` key instead, Linux Lab has remapped `CTRL+Right` to `CTRL+w` and `CTRL+Left` to `CTRL+p`.

6.3.3 How to delete typo in shell command line

Long keypress not work in novnc client currently, so, long `Delete` not work, please use `alt+delete` OR `alt+backspace` instead, more tips:

Function	VIM	Bash
begin/end	<code>^/\$</code>	<code>Ctrl + a/e</code>
forward/backward	<code>w/b</code>	<code>Ctrl + Home/end</code>
cut one word backward	<code>db</code>	<code>Alt + Delete/backspace</code>
cut one word forward	<code>dw</code>	<code>Alt + d</code>
cut all to begin	<code>d^</code>	<code>Ctrl + u</code>
cut all to end	<code>d\$</code>	<code>Ctrl + k</code>
paste all cutted	<code>p</code>	<code>Ctrl + y</code>

6.3.4 Language input switch shortcuts

In order to switch English/Chinese input method, please use `CTRL+s` shortcuts, it is used instead of `CTRL+space` to avoid conflicts with local system.

6.3.5 How to tune the screen size

There are tow methods to tune the screen size, one is auto scaling by noVNC, another is pre-setting during launching.

The first one is setting noVNC before connecting.

- Press the left sidebar of noVNC web page
- Disconnect
- Enable 'Auto Scaling Mode' via 'Settings -> Scaling Mode: -> Local Scaling -> Apply'
- Connect

The second one is setting `SCREEN_SIZE` while running Linux Lab.

The screen size of lab is captured by `xrandr`, if not work, please check and set your own, for example:

Get available screen size values:

```
1 $ xrandr --current
2 Screen 0: minimum 1 x 1, current 1916 x 891, maximum 16384 x 16384
3 Virtual1 connected primary 1916x891+0+0 (normal left inverted right x axis y axis) 0mm x
   0mm
4   1916x891      60.00*+
5   2560x1600    59.99
6   1920x1440    60.00
7   1856x1392    60.00
8   1792x1344    60.00
9   1920x1200    59.88
10  1600x1200    60.00
11  1680x1050    59.95
12  1400x1050    59.98
13  1280x1024    60.02
14  1440x900     59.89
15  1280x960     60.00
16  1360x768     60.02
17  1280x800     59.81
18  1152x864     75.00
19  1280x768     59.87
20  1024x768     60.00
21  800x600      60.32
22  640x480      59.94
```

Update remote screen size:

```
1 $ cd /path/to/cloud-lab
2 $ tools/docker/resize 1280x1024 # Specifiy anyone above
3 $ tools/docker/resize          # If no argument, Sync with host system
```

If want fullscreen, follow these steps:

1. If using virtual machine, fullscreen virtual machine at fist
2. Run `tools/docker/resize` to resize remote lab screen size
3. Enter into WebVNC Interface, Click the FullScreen button at the left sidebar

6.3.6 How to work in fullscreen mode

Open the left sidebar, press the ‘Fullscreen’ button.

6.3.7 How to record video

- Enable recording

Open the left sidebar, press the ‘Settings’ button, config ‘File/Title/Author/Category/Tags/Description’ and enable the ‘Record Screen’ option.

- Start recording

Press the ‘Connect’ button.

- Stop recording

Press the ‘Disconnect’ button.

- Replay recorded video

Press the ‘Play’ button.

- Share it

Videos are stored in ‘cloud-lab/recordings’, share it with help from showdesk.io.

6.3.8 Linux Lab not response

The VNC connection may hang for some unknown reasons and therefore Linux Lab may not response sometimes, to restore it, please press the flush button of web browser or re-connect after explicitly disconnect.

6.3.9 VNC login with failures

If VNC login return “Disconnect timeout”, wait a while and press the left ‘Connect’ button again, otherwise, check as following:

At first, check the containers’ status (Up: Ok, Exit: Bad):

```
1 $ docker ps -a
2 CONTAINER ID IMAGE COMMAND CREATED STATUS PORTS NAMES
3 19a61ba075b5 tinylab/linux-lab "/tools/lab/run" 4 days ago Up 4 days 22/tcp, 5900/tcp
   linux-lab-21575
4 75dae89984c9 tinylab/cloud-ubuntu-web "/startup.sh" 8 days ago Up 8 days ...443/tcp
   cloud-ubuntu-web
```

If the status is ‘Exit’, that means container may be shutdown or may never up, run it again to resume for the shutdown case:


```
1 $ tools/docker/run linux-lab
```

Otherwise, check the running logs:

```
1 $ tools/docker/logs linux-lab
```

If normal, that means the login account and password may have been invalid for some exceptions, please regenerate new account and password with the coming steps:

Note: The `clean` command will remove some containers and data, please do necessary backup before run it, for example, save the container:

```
1 $ tools/docker/save linux-lab
```

VNC login fails while using mismatched password, to fix up such issue, please clean up all and rerun it:

```
1 $ tools/docker/clean linux-lab
2 $ tools/docker/rerun linux-lab
```

If the above command not work, please try this one (**It will clean more data, please do necessary backup**)

```
1 $ tools/docker/clean-all
2 $ tools/docker/rerun linux-lab
```

6.3.10 Ubuntu Snap Issues

Users report many snap issues, please use `apt-get` instead:

- users can not be added to docker group and break non-root operation.
- snap service exhausts the `/dev/loop` devices and break mount operation.

6.3.11 How to exit fullscreen mode of vnc clients

The easiest method is kill the VNC server in Linux Lab:

```
1 $ sudo pkill x11vnc
```

6.4 Lab Issues

6.4.1 No working init found

This means the `rootfs.ext2` image may be broken, please remove it and try `make boot` again, for example:

```
1 $ rm boards/aarch64/raspi3/bsp/root/2019.02.2/rootfs.ext2
2 $ make boot
```

`make boot` command can create this image automatically.

6.4.2 linux/compiler-gcc7.h: No such file or directory

This means using a newer gcc than the one Linux kernel version supported, the solution is switching to an older gcc version via `make gcc-switch`, use `i386/pc` board as an example:

```
1 $ make gcc-list
2 $ make gcc-switch CCORl=internal GCC=4.4
```

6.4.3 linux-lab/configs: Permission denied

This may happen at `make boot` while the repository is cloned with `root` user, please simply update the owner of `cloud-lab/` directory:

```
1 $ cd /path/to/cloud-lab
2 $ sudo chown <USER>:<USER> -R ./
3 $ tools/docker/rerun linux-lab
```

Notes: To make a consistent working environment, Linux Lab only support using as general user: 'ubuntu'.

6.4.4 scripts/Makefile.headersinst: Missing UAPI file

This means MAC OSX not use Case sensitive filesystem, create one using `hdiutil` or Disk Utility yourself:

```
1 $ hdiutil create -type SPARSE -size 60g -fs "Case-sensitive Journaled HFS+" -volname
   labspace labspace.dmg
2 $ hdiutil attach -mountpoint ~/Develop/labspace -nobrowse labspace.dmg.sparseimage
3 $ cd ~/Develop/labspace
```

6.4.5 unable to create file: net/netfilter/xt_dscp.c

This means Windows not enable filesystem's case sensitive feature, just enable it:

```
1 $ cd /path/to/cloud-lab
2 $ fsutil file SetCaseSensitiveInfo ./ enable
```

6.4.6 how to run as root

By default, no password required to run as root with:

```
1 $ sudo -s
```

Notes: Please don't use the 'su' command.

6.4.7 not in supported list

Such information means the specified value is not supported currently:

```
1 $ make boot ROOTDEV=vda
2 ERR: /dev/vda not in supported ROOTDEV list: /dev/sda /dev/ram0 /dev/nfs, update may help
   : 'make bsp B=mips64el/ls3a7a'. Stop.
3
4 $ make boot LINUX=v5.8
5 Makefile:594: *** ERR: v5.8 not in supported Linux list: loongnix-release-1903 v5.7,
   clone one please: 'make kernel-clone KERNEL_NEW=v5.8'. Stop.
6
7 $ make boot QEMU=loongson-v1.1
8 Makefile:606: *** ERR: loongson-v1.1 not in supported QEMU list: loongson-v1.0, clone one
   please: 'make qemu-clone QEMU_NEW=loongson-v1.1'.
```

There are two main types:

- One is the specified version is not there or has not been verified
 - Please clone one and verify it with the usage of `xxx-clone` from section 5.
- Another is the specified value is invalid or simply not verified
 - For example, the above vda is not added in the `ROOTDEV_LIST`
 - This board may not support such type of device or just nobody verify and add it
 - This differs from board and kernel version

6.4.8 is not a valid rootfs directory

If using prebuilt filesystem, this error means the rootfs dir, ramdisk or harddisk creating procedure has been interrupted by `CTRL+C` or similar operations and it means the filesystem is not complete. If no important changes in BSP repository, reset it may help:

```
1 $ make bsp-cleanup
```

If using external filesystem, please make sure the filesystem architecture follows the Linux standards.

7. Contact and Sponsor

7.1 Contact Us

Welcome to join our discuss group:

- Wechat: **tinylab**
- Email: `contact /AT tinylab /dot/ org`

7.2 Give me a star

Welcome to mark our web site, star our git repositories:

- Wechat Group: Tinylab-Org
- Web site: <https://tinylab.org>
 - Created near 10+ years
 - Focus on Linux kernel and embedded Linux system
- Git Repositories
 - Gitee: <https://gitee.com/tinylab>
 - Github: <https://github.com/tinyclub>

7.3 Buy our products

- Store: <https://shop155917374.taobao.com>
 - The taobao store of TinyLab.org community, mainly sell products around our open source projects
 - The products include Linux Lab Disk, Pocket Linux Disk and the Linux Lab boards
 - Welcome to buy some based on your requirement, you can search ‘Linux Lab’ in taobao application to find us
- Circle: <https://t.zsxq.com/uB2vJyF>
 - The VIP knowledge channel of TinyLab.org community
 - Create 3+ years, about 1000+ shares and 20+ Linux professionals
- Courses: <https://m.cctalk.com/inst/sh8qtdag>
 - TinyLab School – The video channel of TinyLab.org community
 - Video Live, Video Courses are shared by active Linux professionals from TinyLab.org community

7.4 Sponsor

7.4.1 Sponsor via wechat



联系我们



捐赠项目

Figure 3: contact-sponsor

7.4.2 Sponsor list

- 2022
 - [Summer 2022](#)
 - * Sponsored projects: [Microbench](#), [OpenHW Lab](#), [PWN Lab](#)
 - PLCT Lab
 - * 2 D1 boards
 - * Sponsored [RISC-V Linux Project](#)
- 2021
 - [Lazyparser](#)
 - * HelloGCC and HelloLLVM founder
 - * 5000RMB
 - [Summer 2021](#)
 - * Sponsored projects: Rust for Linux, openEuler Kernel for aarch64/virt and x86_64/pc
 - T-head
 - * 1 D1 board
 - Allwinner
 - * 3 D1 boards
- 2020

- [Loongson](#)
 - * The famous Chinese Loongson CPU designer and manufacturer
 - * Sponsored boards: mips64el/ls2k, mips64el/ls3a7a, mipsel/ls1b, mipsel/ls232
- [Summer 2020](#)
 - * Sponsored projects: Linux Lab docker image upgrade from Ubuntu 14.04 to Ubuntu 20.04
- [Embedfire](#)
 - * 6 imx6ull boards